

## [FAQ]

# What is the arrow icon overlaid on the bottom-right corner of the recordings?


Article ID: GV11-10-28-j

Release Date: 10/28/2011

### Applied to

GV-System V8.2 or later

### Question

An **Arrow** icon  appeared and overlaid on the bottom-right corner of the recorded videos.


What does it mean?



## Answer

The **Arrow** icon  means the **Noise detection to reduce file size** function was enabled.

When this function is enabled, the GV-System will automatically reduce recording size on video noise conditions, and restore normal recording size when the disturbing conditions are over. The Arrow icon overlaid on the recordings is for you to easily distinguish the normal-size segment from reduced-size segment.






## How to do


To enable the **Noise detection to reduce file size** function, follow the steps below.

**Note:** The instructions below are based on GV-System V8.5 in which some menu options and user interfaces are different from previous versions.


1. On the Main System, click the **Configure** button, select **System Configure** and select **Camera Configure**. This dialog box appears.



2. Enable **Rec. Video**, select a recording mode, click the **right-arrow** button  and select **Codec Settings**.
3. Enable **Apply Advanced Codec Setting** and click the  button.



4. Select **Noise detection to reduce file size** and adjust the **Sensitivity** level. The higher the value, the more sensitive the system is to video noise.



5. Click **Apply**.